Chapter 3: Processes



Chapter 3: Processes

- Process Concept
- Process Scheduling
- Operations on Processes
- Interprocess Communication
- IPC in Shared-Memory Systems
- IPC in Message-Passing Systems
- Examples of IPC Systems
- Communication in Client-Server Systems

Objectives

- Identify the separate components of a process and illustrate how they are represented and scheduled in an operating system.
- Describe how processes are created and terminated in an operating system, including developing programs using the appropriate system calls that perform these operations.
- Describe and contrast interprocess communication using shared memory and message passing.
- Design programs that uses pipes and POSIX shared memory to perform interprocess communication.
- Describe client-server communication using sockets and remote procedure calls.
- Design kernel modules that interact with the Linux operating system.

Process Concept

- An operating system executes a variety of programs that run as a process.
- **Process** – a program in execution; process execution must progress in sequential fashion
- Multiple parts
  - The program code, also called **text section**
  - Current activity including **program counter**, processor registers
  - **Stack** containing temporary data
    - Function parameters, return addresses, local variables
  - **Data section** containing global variables
  - **Heap** containing memory dynamically allocated during run time

Process Concept (Cont.)

- Program is ***passive*** entity stored on disk (**executable file**); process is ***active***
  - Program becomes process when executable file loaded into memory
- Execution of program started via GUI mouse clicks, command line entry of its name, etc
- One program can be several processes
  - Consider multiple users executing the same program

Process in Memory



Memory Layout of a C Program



Process Control Block (PCB)

Information associated with each process

(also called **task control block**)

- Process state – running, waiting, etc
- Program counter – location of instruction to next execute
- CPU registers – contents of all process-centric registers
- CPU scheduling information- priorities, scheduling queue pointers
- Memory-management information – memory allocated to the process
- Accounting information – CPU used, clock time elapsed since start, time limits
- I/O status information – I/O devices allocated to process, list of open files

Process State

- As a process executes, it changes **state**
  - **New**: The process is being created
  - **Running**: Instructions are being executed
  - **Waiting**: The process is waiting for some event to occur
  - **Ready**: The process is waiting to be assigned to a processor
  - **Terminated**: The process has finished execution

Threads

- So far, process has a single thread of execution
- Consider having multiple program counters per process
  - Multiple locations can execute at once
    - Multiple threads of control -> **threads**
- Must then have storage for thread details, multiple program counters in PCB

Diagram of Process State



dispatch: ทำการส่งข่าวสาร

Process Representation in Linux

Represented by the C structure `task_struct`

```
pid t_pid;                    /* process identifier */
long state;                   /* state of the process */
unsigned int time_slice       /* scheduling information */
struct task_struct *parent;/* this process's parent */
struct list_head children; /* this process's children */
struct files_struct *files;/* list of open files */
struct mm_struct *mm;         /* address space of this process */
```



Process Scheduling

- Maximize CPU use, quickly switch processes onto CPU core
- **Process scheduler** selects among available processes for next execution on CPU core
- Maintains **scheduling queues** of processes
  - **Ready queue** – set of all processes residing in main memory, ready and waiting to execute
  - **Wait queues** – set of processes waiting for an event (i.e. I/O)
  - Processes migrate among the various queues

CPU Switch From Process to Process

A **context switch** occurs when the CPU switches from one process to another.



Ready and Wait Queues



Context Switch

- When CPU switches to another process, the system must **save the state** of the old process and load the **saved state** for the new process via a **context switch**
- **Context** of a process represented in the PCB
- Context-switch time is overhead; the system does no useful work while switching
  - The more complex the OS and the PCB ➔ the longer the context switch
- Time dependent on hardware support
  - Some hardware provides multiple sets of registers per CPU ➔ multiple contexts loaded at once

Representation of Process Scheduling



Queueing-diagram

Multitasking in Mobile Systems

- Some mobile systems (e.g., early version of iOS) allow only one process to run, others suspended
- Due to screen real estate, user interface limits iOS provides for a
  - Single **foreground** process- controlled via user interface
  - Multiple **background** processes– in memory, running, but not on the display, and with limits
  - Limits include single, short task, receiving notification of events, specific long-running tasks like audio playback
- Android runs foreground and background, with fewer limits
  - Background process uses a **service** to perform tasks
  - Service can keep running even if background process is suspended
  - Service has no user interface, small memory use

Operations on Processes

- System must provide mechanisms for:
  - process creation
  - process termination

Process Creation

- **Parent** process create **children** processes, which, in turn create other processes, forming a **tree** of processes
- Generally, process identified and managed via a **process identifier** (**pid**)
- Resource sharing options
  - Parent and children share all resources
  - Children share subset of parent's resources
  - Parent and child share no resources
- Execution options
  - Parent and children execute concurrently
  - Parent waits until children terminate

A Tree of Processes in Linux



Process Creation (Cont.)

- Address space
  - Child duplicate of parent
  - Child has a program loaded into it
- UNIX examples
  - `fork()` system call creates new process
  - `exec()` system call used after a `fork()` to replace the process' memory space with a new program
  - Parent process calls `wait()` for the child to terminate



C Program Forking Separate Process

```c
#include <sys/types.h>
#include <stdio.h>
#include <unistd.h>

int main()
{
pid_t pid;

   /* fork a child process */
   pid = fork();

   if (pid < 0) { /* error occurred */
     fprintf(stderr, "Fork Failed");
     return 1;
   }
   else if (pid == 0) { /* child process */
     execlp("/bin/ls","ls",NULL);
   }
   else { /* parent process */
     /* parent will wait for the child to complete */
     wait(NULL);
     printf("Child Complete");
   }

   return 0;
}
```


Creating a Separate Process via Windows API

```c
#include <stdio.h>
#include <windows.h>

int main(VOID)
{
STARTUPINFO si;
PROCESS_INFORMATION pi;

   /* allocate memory */
   ZeroMemory(&si, sizeof(si));
   si.cb = sizeof(si);
   ZeroMemory(&pi, sizeof(pi));

   /* create child process */
   if (!CreateProcess(NULL, /* use command line */
    "C:\\WINDOWS\\system32\\mspaint.exe", /* command */
    NULL, /* don't inherit process handle */
    NULL, /* don't inherit thread handle */
    FALSE, /* disable handle inheritance */
    0, /* no creation flags */
    NULL, /* use parent's environment block */
    NULL, /* use parent's existing directory */
    &si,
    &pi))
   {
     fprintf(stderr, "Create Process Failed");
     return -1;
   }
   /* parent will wait for the child to complete */
   WaitForSingleObject(pi.hProcess, INFINITE);
   printf("Child Complete");

   /* close handles */
   CloseHandle(pi.hProcess);
   CloseHandle(pi.hThread);
}
```

Process Termination

- Process executes last statement and then asks the operating system to delete it using the `exit()` system call.
  - Returns status data from child to parent (via `wait()`)
  - Process' resources are deallocated by operating system
- Parent may terminate the execution of children processes using the `abort()` system call. Some reasons for doing so:
  - Child has exceeded allocated resources
  - Task assigned to child is no longer required
  - The parent is exiting and the operating systems does not allow a child to continue if its parent terminates

Process Termination

- Some operating systems do not allow child to exists if its parent has terminated. If a process terminates, then all its children must also be terminated.
  - **cascading termination.** All children, grandchildren, etc. are terminated.
  - The termination is initiated by the operating system.
- The parent process may wait for termination of a child process by using the `wait()` system call. The call returns status information and the pid of the terminated process

```
pid = wait(&status);
```

- If no parent waiting (did not invoke `wait()`) process is a zombie
- If parent terminated without invoking `wait`, process is an orphan

Android Process Importance Hierarchy

- Mobile operating systems often have to terminate processes to reclaim system resources such as memory. From **most** to **least** important:
  - Foreground process
  - Visible process
  - Service process
  - Background process
  - Empty process
- Android will begin terminating processes that are least important.

Multiprocess Architecture – Chrome Browser

- Many web browsers ran as single process (some still do)
  - If one web site causes trouble, entire browser can hang or crash
- Google Chrome Browser is multiprocess with 3 different types of processes:
  - **Browser** process manages user interface, disk and network I/O
  - **Renderer** process renders web pages, deals with HTML, Javascript. A new renderer created for each website opened
    - Runs in **sandbox** restricting disk and network I/O, minimizing effect of security exploits
  - **Plug-in** process for each type of plug-in



Interprocess Communication

- Processes within a system may be ***independent*** or ***cooperating***
- Cooperating process can affect or be affected by other processes, including sharing data
- Reasons for cooperating processes:
  - Information sharing
  - Computation speedup
  - Modularity
  - Convenience
- Cooperating processes need **interprocess communication** (**IPC**)
- Two models of IPC
  - **Shared memory**
  - **Message passing**

Communications Models

(a) Shared memory. (b) Message passing.



Cooperating Processes

- ***Independent*** process cannot affect or be affected by the execution of another process
- ***Cooperating*** process can affect or be affected by the execution of another process
- Advantages of process cooperation
  - Information sharing
  - Computation speed-up
  - Modularity
  - Convenience

Producer-Consumer Problem

- Paradigm for cooperating processes, *producer* process produces information that is consumed by a *consumer* process
  - unbounded-buffer places no practical limit on the size of the buffer
  - bounded-buffer assumes that there is a fixed buffer size

Interprocess Communication – Shared Memory

- An area of memory shared among the processes that wish to communicate
- The communication is under the control of the users processes not the operating system.
- Major issues is to provide mechanism that will allow the user processes to synchronize their actions when they access shared memory.

Bounded-Buffer – Shared-Memory Solution

- Shared data

```
#define BUFFER_SIZE 10
typedef struct {
  . . .
} item;

item buffer[BUFFER_SIZE];
int in = 0;
int out = 0;
```



- Solution is correct, but can only use `BUFFER_SIZE-1` elements

in :point the next free position in the buffer
out: point the first full position in the buffer
buffer empty when in==out
buffer full when ((in+1) % BUFFER_SIZE)== out)
% is modulus operator Ex. 3 %10 = 3

Producer Process – Shared Memory




```
item next_produced;

while (true) {
   /* produce an item in next produced */
   while (((in + 1) % BUFFER_SIZE) == out); /* do nothing- no free
                                               buffers */
   buffer[in] = next_produced;
   in = (in + 1) % BUFFER_SIZE;
}
```

in :point the next free position in the buffer
out: point the first full position in the buffer
buffer empty when in==out
buffer full when ((in+1) % BUFFER_SIZE)== out)
% is modulus operator Ex. 3 %10 = 3

Consumer Process – Shared Memory




```
item next_consumed;

while (true) {
        while (in == out); /* do nothing -nothing to consume*/

           /* remove an item from the buffer  */
        next_consumed = buffer[out];
        out = (out + 1) % BUFFER_SIZE;

        /* consume the item in next consumed */
}
```

in :point the next free position in the buffer
out: point the first full position in the buffer
buffer empty when in==out

Interprocess Communication – Message Passing

- Mechanism for processes to communicate and to synchronize their actions
- Message system – processes communicate with each other without resorting to shared variables
- IPC facility provides two operations:
  - `send`(*message*)
  - `receive`(*message*)
- The *message* size is either fixed or variable

Message Passing (Cont.)

- If processes *P* and *Q* wish to communicate, they need to:
  - Establish a ***communication link*** between them
  - Exchange messages via send/receive
- Implementation issues:
  - How are links established?
  - Can a link be associated with more than two processes?
  - How many links can there be between every pair of communicating processes?
  - What is the capacity of a link?
  - Is the size of a message that the link can accommodate fixed or variable?
  - Is a link unidirectional or bi-directional?

Message Passing (Cont.)

- Implementation of communication link
  - Physical:
    - Shared memory
    - Hardware bus
    - Network
  - Logical:
    - Direct or indirect
    - Synchronous or asynchronous
    - Automatic or explicit buffering

Direct Communication

- Processes must name each other explicitly:
  - `send` (*P, message*) – send a message to process P
  - `receive`(*Q, message*) – receive a message from process Q
- Properties of communication link
  - Links are established automatically
  - A link is associated with exactly one pair of communicating processes
  - Between each pair there exists exactly one link
  - The link may be unidirectional, but is usually bi-directional

Indirect Communication

- Messages are directed and received from mailboxes (also referred to as ports)
  - Each mailbox has a unique id
  - Processes can communicate only if they share a mailbox
- Properties of communication link
  - Link established only if processes share a common mailbox
  - A link may be associated with many processes
  - Each pair of processes may share several communication links
  - Link may be unidirectional or bi-directional

Indirect Communication

- Operations
  - create a new mailbox (port)
  - send and receive messages through mailbox
  - destroy a mailbox
- Primitives are defined as:

  `send`(*A, message*) – send a message to mailbox A

  `receive`(*A, message*) – receive a message from mailbox A

Indirect Communication

- Mailbox sharing
  - P_1, P_2, and P_3 share mailbox A
  - P_1, sends; P_2 and P_3 receive
  - Who gets the message?
- Solutions
  - Allow a link to be associated with at most two processes
  - Allow only one process at a time to execute a receive operation
  - Allow the system to select arbitrarily the receiver. Sender is notified who the receiver was.

Synchronization

- Message passing may be either blocking or non-blocking
- **Blocking** is considered **synchronous**
  - **Blocking send** -- the sender is blocked until the message is received
  - **Blocking receive** -- the receiver is blocked until a message is available
- **Non-blocking** is considered **asynchronous**
  - **Non-blocking send** -- the sender sends the message and continue
  - **Non-blocking receive** -- the receiver receives:
    - A valid message, or
    - Null message
- Different combinations possible
  - If both send and receive are blocking, we have a **rendezvous**

rendezvous : จุดนัดพบ

Producer – Shared Memory

```
message next_produced;

while (true) {
      /* produce an item in next_produced */

       send(next_produced);
}
```


Consumer– Shared Memory

```
message next_consumed;

while (true) {
      receive(next_consumed)

      /* consume the item in next_consumed */
 }
```


Buffering

- Queue of messages attached to the link.
- Implemented in one of three ways
  1. Zero capacity – no messages are queued on a link. Sender must wait for receiver (rendezvous)
  2. Bounded capacity – finite length of *n* messages Sender must wait if link full
  3. Unbounded capacity – infinite length Sender never waits

rendezvous : จุดนัดพบ
finite: จำกัด
infinite: ไม่จำกัด

Examples of IPC Systems - POSIX

- POSIX Shared Memory
  - Process first creates shared memory segment
    `shm_fd = shm_open(name, O CREAT | O RDWR, 0666);`
  - Also used to open an existing segment
  - Set the size of the object

`ftruncate(shm_fd, 4096);`

  - Use `mmap()` to memory-map a file pointer to the shared memory object
  - Reading and writing to shared memory is done by using the pointer returned by `mmap()`.

IPC POSIX Producer

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <fcntl.h>
#include <sys/shm.h>
#include <sys/stat.h>

int main()
{
/* the size (in bytes) of shared memory object */
const int SIZE = 4096;
/* name of the shared memory object */
const char *name = "OS";
/* strings written to shared memory */
const char *message_0 = "Hello";
const char *message_1 = "World!";

/* shared memory file descriptor */
int shm_fd;
/* pointer to shared memory obect */
void *ptr;

   /* create the shared memory object */
   shm_fd = shm_open(name, O_CREAT | O_RDWR, 0666);

   /* configure the size of the shared memory object */
   ftruncate(shm_fd, SIZE);

   /* memory map the shared memory object */
   ptr = mmap(0, SIZE, PROT_WRITE, MAP_SHARED, shm_fd, 0);

   /* write to the shared memory object */
   sprintf(ptr,"%s",message_0);
   ptr += strlen(message_0);
   sprintf(ptr,"%s",message_1);
   ptr += strlen(message_1);

   return 0;
}
```


IPC POSIX Consumer

```
#include <stdio.h>
#include <stdlib.h>
#include <fcntl.h>
#include <sys/shm.h>
#include <sys/stat.h>

int main()
{
/* the size (in bytes) of shared memory object */
const int SIZE = 4096;
/* name of the shared memory object */
const char *name = "OS";
/* shared memory file descriptor */
int shm_fd;
/* pointer to shared memory obect */
void *ptr;

   /* open the shared memory object */
   shm_fd = shm_open(name, O_RDONLY, 0666);

   /* memory map the shared memory object */
   ptr = mmap(0, SIZE, PROT_READ, MAP_SHARED, shm_fd, 0);

   /* read from the shared memory object */
   printf("%s",(char *)ptr);

   /* remove the shared memory object */
   shm_unlink(name);

   return 0;
}
```


Examples of IPC Systems - Mach

- Mach communication is message based
  - Even system calls are messages
  - Each task gets two ports at creation- Kernel and Notify
  - Messages are sent and received using the **`mach_msg()`** function
  - Ports needed for communication, created via **`mach_port_allocate()`**
  - Send and receive are flexible, for example four options if mailbox full:
    - Wait indefinitely
    - Wait at most n milliseconds
    - Return immediately
    - Temporarily cache a message

Mach Messages

```
#include<mach/mach.h>

struct message {
      mach_msg_header_t header;
      int data;
};

mach port t client;
mach port t server;
```


Mach Message Passing - Client

```
    /* Client Code */

struct message message;

// construct the header
message.header.msgh_size = sizeof(message);
message.header.msgh_remote_port = server;
message.header.msgh_local_port = client;

// send the message
mach_msg(&message.header, // message header
  MACH_SEND_MSG, // sending a message
  sizeof(message), // size of message sent
  0, // maximum size of received message - unnecessary
  MACH_PORT_NULL, // name of receive port - unnecessary
  MACH_MSG_TIMEOUT_NONE, // no time outs
  MACH_PORT_NULL // no notify port
);
```


Mach Message Passing - Server

```
    /* Server Code */

struct message message;

// receive the message
mach_msg(&message.header, // message header
  MACH_RCV_MSG, // sending a message
  0, // size of message sent
  sizeof(message), // maximum size of received message
  server, // name of receive port
  MACH_MSG_TIMEOUT_NONE, // no time outs
  MACH_PORT_NULL // no notify port
);
```

Examples of IPC Systems – Windows

- Message-passing centric via **advanced local procedure call** (**LPC**) facility
  - Only works between processes on the same system
  - Uses ports (like mailboxes) to establish and maintain communication channels
  - Communication works as follows:
    - The client opens a handle to the subsystem's **connection port** object.
    - The client sends a connection request.
    - The server creates two private **communication ports** and returns the handle to one of them to the client.
    - The client and server use the corresponding port handle to send messages or callbacks and to listen for replies.

Local Procedure Calls in Windows



Communications in Client-Server Systems

- Sockets
- Remote Procedure Calls

Sockets

- A **socket** is defined as an endpoint for communication
- Concatenation of IP address and **port** – a number included at start of message packet to differentiate network services on a host
  - Ex. ftp port: 21, telnet port: 23 , http port: 80
- The socket **161.25.19.8:1625** refers to port **1625** on host **161.25.19.8**
- Communication consists between a pair of sockets
- All ports below 1024 are ***well known***, used for standard services
- Special IP address 127.0.0.1 (**loopback**) to refer to system on which process is running

Socket Communication



Sockets in Java

- Three types of sockets
  - **Connection-oriented** (**TCP**)
  - **Connectionless** (**UDP**)
  - **MulticastSocket** class– data can be sent to multiple recipients
- Consider this "Date" server in Java:

```
import java.net.*;
import java.io.*;

public class DateServer
{
   public static void main(String[] args) {
      try {
        ServerSocket sock = new ServerSocket(6013);

        /* now listen for connections */
        while (true) {
           Socket client = sock.accept();

           PrintWriter pout = new
            PrintWriter(client.getOutputStream(), true);

           /* write the Date to the socket */
           pout.println(new java.util.Date().toString());

           /* close the socket and resume */
           /* listening for connections */
           client.close();
        }
      }
      catch (IOException ioe) {
        System.err.println(ioe);
      }
   }
}
```

Sockets in Java

The equivalent Date client

```
import java.net.*;
import java.io.*;

public class DateClient
{
   public static void main(String[] args) {
      try {
         /* make connection to server socket */
         Socket sock = new Socket("127.0.0.1",6013);

         InputStream in = sock.getInputStream();
         BufferedReader bin = new
            BufferedReader(new InputStreamReader(in));

         /* read the date from the socket */
         String line;
         while ( (line = bin.readLine()) != null)
            System.out.println(line);

         /* close the socket connection*/
         sock.close();
      }
      catch (IOException ioe) {
         System.err.println(ioe);
      }
   }
}
```


Remote Procedure Calls

- Remote procedure call (RPC) abstracts procedure calls between processes on networked systems
  - Again uses ports for service differentiation
- **Stubs** – client-side proxy for the actual procedure on the server
- The client-side stub locates the server and **marshalls** the parameters
- The server-side stub receives this message, unpacks the marshalled parameters, and performs the procedure on the server
- On Windows, stub code compile from specification written in **Microsoft Interface Definition Language** (**MIDL**)

Remote Procedure Calls (Cont.)

- Data representation handled via **External Data Representation** (**XDL**) format to account for different architectures
  - **Big-endian** and **little-endian**
- Remote communication has more failure scenarios than local
  - Messages can be delivered ***exactly once*** rather than ***at most once***
- OS typically provides a rendezvous (or **matchmaker**) service to connect client and server

Execution of RPC



End of Chapter 3